

Trouble Shooting

- When preparing to (import) capture your clips, you should have a black screen. Blue screens indicate that you have an equipment/ technical correction problem and you cannot import. Here are some trouble shooting suggestions.
1. Go to Project, Project Settings, Capture, and then Settings. Under Video Input make sure the file is set up as *composite* and not *s-video*.
 2. If the blue screen is still present, unplug all cables, make sure they are clean, and then plug them in again.

REMEMBER!!

When using the VHS adaptor, don't forget to keep the VCR's channel on L-1. The ZR80's channel must be F-1.

About Adobe Premiere

Adobe Premiere's digital editing program has sharper imaging with a higher quality and number of pixels per image.

Adobe Premiere is loaded with hundreds of special effects for your imported video clips; including video and audio effects.

Experiment!!

**MOST
IMPORTANTLY,
HAVE FUN!!**

IMPORTING Video Clips Using Adobe Premiere



Prepared by

Jasmine Palmer & Danielle Crais
Advanced Multimedia Productions
Luther Jackson Middle School

*Before editing your video, you must first know the specific steps of importing clips using Adobe Premiere.


- On the desktop, go to my computer.
- Go to Video (E:)
 - right click new
 - select folder
 - name folder of project
- Select Adobe Premiere on the desktop.
- Go to edit on the Toolbar.
- Select Preferences
- Scratch disk
- Change all folders' location to the name of your project folder.

To import clips using the Canon ZR Digital Cameras

- To import from the Canon ZR 20-80 digital cameras, use the mini DV tapes.
- Plug the cables into the input VCR, left to right in this order~
YELLOW, WHITE, RED
- Turn on the camera and make sure it's on *play mode*.
- On the toolbar at the top of the screen, go to File, and select Capture.
- Find desired clip on your tape and select record on the box on the computer screen.
- After your clip has been captured, you will find it in the bin.

To import clips using a Video Camcorder

- To import from the video camcorders, insert your video cassette into the VCR adaptor and place it in the Input VCR.
- On the toolbar, at the top of the screen, go to File, and select Movie Capture.
- Find desired clip on your tape and select record on the box on the computer screen.
- The clip will be in the bin.



This is the bin where you'll find your imported video clips.