



WindowsRT (SurfacePro) Device Configuration

Fairfax County Public Schools Secure Wireless

The purpose of this document is to outline the steps of using the FCPSonboard wireless network to correctly configure your device to connect to the Fairfax network.



From Start go to the Desktop. Open the list of available networks and Connect to FCPSonboard.






The Windows Store App version of IE will automatically come up.
GO TO START AND BACK TO DESKTOP. The Windows Store App [aka Metro] IE is limited in features; it is not compatible with the FCPS wireless onboarding process.



Open Internet Explorer.



You should be redirected to the FCPSonboard wizard. Check the box next to “I agree to the Terms and Conditions” and press the Start button.




Press the Staff and Students button.



Enter the username and password that you use to log on to the computer at school. Press the Continue button. NOTE: if authentication fails the account may be locked out, or the password may be expired.




Click Personal Devices.




Scroll down to the Other Operating Systems section and press Step 1: Install the CA Certificate.



Press Open.



Press Open.




Press Open.



Press Install Certificate.



Press Next.



Press Next.




Press Finish.



Press OK.



Press OK




Press Step 2: Install Your Certificate and then, on the box that appears at the bottom, Press Open.



Press Open.



Press Next.



Press Next.



Enter the password that you use to log on to the computer at school and press Next.



Press Yes.



Press Next.



Press Finish




Press OK.




Open the Network and Sharing Center. To do this please Right click on the wireless icon in the bottom right of your task bar. Then click Open Network and Sharing Center.




Click on Set up a new connection or network.



Select Manually connect to a wireless network and press Next.



Enter in the network name Fairfax, which is case sensitive, use a capital F, and security type WPA2-Enterprise. Other settings leave default. Press Next.




Press Change connection settings.



Press the Security tab. Change Choose a network authentication method option to Microsoft: Smart Card or other certificate. Press Settings.



Check box next to FCPS Root CA under the Trusted Root Certification Authorities option. Press Ok. Press Ok again and then press Close.



Click on the wireless network icon in the System Tray and choose the Fairfax network.



Make sure that the “Connect automatically” box is checked. Select Connect.